



Diagnosics and bleeding localization

Estimate of blood loss:

- Less severe: 500 - 1000 ml
- Severe: more than 1000 ml
- Peripartum hemorrhage: rapidly increasing blood loss, clinically estimated to be above 1500 ml or as any blood loss associated with the development of clinical and/or laboratory signs of shock/tissue hypoperfusion

Organization of care according to estimated blood loss:

- Less severe blood loss=An obstetrician is always called
- Severe blood loss=An anesthesiologist is always called in
- Peripartum hemorrhage=A multidisciplinary crisis team is always activated

Identification of the source of bleeding:

1. Palpation / bimanual examination
2. Examination in mirrors
3. Ultrasound examination

Other procedures:

1. Assessment and stabilization of basic vital signs
2. Start monitoring of basic vital signs
3. Initiation of oxygen therapy
4. Securing/controlling vascular access
5. Initiation of fluid replacement/fluid resuscitation
6. Catheterization of the bladder
7. Consider the following procedures:
 - Uterine massage
 - Bimanual compression of the uterus
 - External aortic compression

Recommended initial laboratory tests:

1. Blood count
2. Coagulation tests (aPTT, PT, antithrombin III)
3. Fibrinogen level
4. Pre-transfusion testing (blood group, screening for irregular erythrocyte antibodies, compatibility test)
5. Consider viscoelastic examination

Initial requirements for transfusion products:

1. Plasma (in the initial phase ensure availability of at least 4 T.U)

2. Erythrocytes (in the initial phase ensure the availability of at least 4 T.U)

Ensuring the stability of the indoor environment:

1. Acid-base balance
2. Temperature
3. Level of ionized calcium (Ca²⁺⁺)

Tromboelastometry provides rapid information on acute hemostatic status, allows differentiation of the causes of bleeding and deployment of targeted treatment.



ENDOWMENT FUND
FOR THE DEVELOPMENT
OF GYNECOLOGY AND OBSTETRICS

SINCE 1991